UniFi Camera Image Archiver & Uploader

Main website: http://www.phoenix125.com/

Download: http://www.phoenix125.com/share/atlas/AtlasServerUpdateUtility.zip Download: http://www.phoenix125.com/share/unificameraimagearchiverftpuploader/UniFiCameralmageArchiverFTPUploader.zip

Features


- Create archives of Ubiquiti UniFi cameras (or any camera with http snapshot).
- Upload images via FTP. Works with Wunderground.

GitHub (Open Source): https://github.com/phoenix125/UniFiCameralmageArchiverFTPUploader

- Resize images for upload and archive.
- Use third-party software to create time-lapse videos from archived images. I personally use AviDemux.
- Works with 1-100 cameras.
- Each camera has independent settings:
 - Save Folder Upload folder
- o Independent archive and FTP frequency

Forum: https://phoenix125.createaforum.com/index.php

Logs of archives and FTPs.






PAGE 1 OF 3 KIM@KIM125.COM 2021-03-06

Instructions


- Run UniFiCameralmageArchiverFTPUploader vX.exe
- Config window will open. Set parameters.
- Click on Camera Number to change camera.
- Hove mouse over any option for details.
- To set Camera Snapshot URL, see instructions below.



How to Enable SnapShot on UniFi cameras

- In a web browser, enter your camera's IP address: ie. 192.168.1.80
- Log in. Username: ubnt Password: (get from UniFi Protect see below for instructions)








2021-03-06 PAGE **2** OF **3**

KIM@KIM125.COM

• Click "Enable Anonymous Snapshot" to enable it. A checkmark will appear.



• Your UniFi camera will now create a snap.jpeg file in the URL's root folder every second or so. To access it, enter http://{IP}/snap.jpeg in any web browser. i.e. http://192.168.1.84/snap.jpeg

Revision History

2021-03-06 v1.2 Config GUI!

- Added: Config GUI
- Added: Separate options for archiving and uploading full size and resized images

2021-02-28 v1.1

- Added: Separate save intervals for each camera
- Added: Optionally add sequential numbers at end of filename instead of date. Useful for some Image-To-Video programs

2020-12-13 v1.0 Initial Release

